

Avigilon™ Control Center 5 Release Notes for Integration with C•CURE 9000

C•CURE Integration 5.6.2.22 – Released February 04, 2016

Release Summary

This integration update adds support for Software House C•CURE 9000 version 2.40, as well as the ability to receive analytics events, display bounding boxes, and export video with embedded bounding boxes from the C•CURE client. It maintains the ability to view live and recorded video and control PTZ devices in the C•CURE 9000 interface. The integration version is certified for C•CURE 9000 Enterprise and Redundancy.

New Features & Issues Fixed

- Added support for C•CURE 9000 v2.40
- Added ability to send analytics events to C•CURE 9000
- Added ability to display analytics bounding boxes within C•CURE 9000 client.
- Added ability to include analytics bounding box overlays in exported video from C•CURE 9000 interface.

Known limitations

- Unable to configure or use Preset and Pattern 0 in triggered alarms or events
- After updating the older integration, the old installation must be manually removed from Windows Add/Remove Program
- When a server goes offline and online again, there can be a delay before it reconnects
- There may be a delay when shutting down the integration via the Crossfire Server Component Framework

Supported versions of ACC

- ACC 5.6.2 and later

Supported versions for C•CURE 9000:

- C•CURE 9000 v2.40, v2.41