

Avigilon™ Control Center 6 Release Notes for Integration with Software House C•CURE 9000 v2.60

C•CURE 9000 integration 6.0.0.24 – Released June 6, 2017

Release Summary

This integration update adds support for Software House C•CURE 9000 version 2.60, as well as the ability to use center and zoom on box drawn by mouse on PTZ cameras which support this functionality in the Avigilon Control Center client. It maintains the ability to view live and recorded video and control PTZ devices in the C•CURE 9000 interface. The integration version is certified for C•CURE 9000 Enterprise and Redundancy.

New Features & Issues Fixed

- Added support for C•CURE 9000 v2.60
- Added ability to use center and zoom on box drawn by mouse for supported PTZ cameras
- Added support for Avigilon server and camera failover

Supported versions of ACC

- ACC 6.0.0.24 and later

Supported versions for C•CURE 9000:

- C•CURE 9000 v2.60

Known limitations

- Unable to configure or use Preset and Pattern 0 in triggered alarms or events
- After updating the older integration, the old installation must be manually removed from Windows Add/Remove Program
- When a server goes offline and online again, there can be a delay before it reconnects
- There may be a delay when shutting down the integration via the Crossfire Server Component Framework
- Click-to-center is only supported on Avigilon PTZ cameras
- Center and zoom on box drawn by mouse is only supported on Avigilon PTZ cameras